

WDM Driver for PD-USB01

Version history

Version 3.0.0.0

- Supports **PD-USB01V1** and **PD-USB01V2**
- Code restructured and optimized
- Support for temperature sensor functionality
- Updated error/warning handling

Version 2.0.0.8

- Fixed bug regarding burst mode under certain conditions
- Increased timeout for I²C operations

Version 2.0.0.6

- Supports connector AUX and digital input3 / output 3 (this functionality requires CPLD version 2.03)

Version 2.0.0.4

- Bug fix in async. operating modes
- Supports CPLD programming via USB device

Version 2.0.0.2

- Bug fix in I2C operation
- Smaller changings in StartDevice and RemoveDevice procedures

Version 2.0.0.0

- Far reaching modifications in controller firmware and device driver
- Modification in driver - application interface (SDACQ32MP DLL >= 1.8.0.0)

Version 1.0.0.8

- I2C operations optimized

April 2008



Version 1.0.0.4

- Some bugfixes
- Enhanced pnp handling
- Improved datastream performance
- Reduced signal jitter
- ISP support

Version 1.0.0.0

- First official release